SUSE Manager 3 Hands-on



Hands-on :: Setup 01

Access the training systems, prepare the system and install the SUMA.

Setup 01 - Login

Connect to the training system with ssh:

```
# ssh "user$nr"@"$hostsystem"
# ssh root@"suma$nr"
```

Setup 01 - Datadisks

Create the data disks and put a file system on the devices:

```
# pvcreate /dev/vdb
# vgcreate vg_data /dev/vdb
# lvcreate -l50%FREE -n lv_database vg_data
# lvcreate -l100%FREE -n lv_spacewalk vg_data
# mkfs.xfs /dev/mapper/vg_data-lv_database
# mkfs.xfs /dev/mapper/vg_data-lv_spacewalk
```

Setup 01 - Mount Datadisks

Delete the BTRFS pgsql subvolume and add the new devies to the /etc/fstab:

```
UUID=9f9e1724-f38a-40f9-8d24-867a24cc8e0f /var/lib/pgsql xfs defau UUID=a13dd737-3042-42fb-9a09-1b88828d2bf5 /var/spacewalk xfs defau
```

Create the mountpoint and mount the new devices:

```
# mkdir /var/spacewalk
# mount -a
```

Setup 01 - Attach the repositories (INET)

If you have internet access (via proxy), register with scc.suse.com:

Setup 01 - Attach the repositories (SMT)

If you don't have internet access, get the repositories from your SMT server:

SUSEConnect -p SUSE-Manager-Server/3.0/x86_64

Setup 01 - Verify the respositories

Check if the SUMA repositories are available on your machine:

zypper repos

Setup 01 - Installation

Verify if the SUMA pattern is available and install it:

```
# zypper search -t pattern suma_server
# zypper info -t pattern suma_server
# zypper install -t pattern suma_server
```

Setup 01 - Setup

Run the yast2 command to start the setup:

yast2 susemanager_setup

Setup 01 - E-mail Address

YaST2 - susemanager_setup @ su	mal		
SUSE Manager			
SUSE Manager Administrator E susemanager@net1.lab	-mail Address		
[] A d vertise SUSE Manager v	ia SLP		
[Help]	[Back]	[Abort]	[Next]
Fl Help F8 Back F9 Abort F1	0 Next		

Setup 01 - Certificate

YaST2 - susemanager_setup @ su	mal		
Certificate Setup			
- cor extracate oc cup			
Organization			<u> </u>
adsy			
Organization Unit			
City			
Bern			
State			
Bern Country			
CH			
SSL Password			

Repeat Password			
100000			
[Help]	[Back]	[Abort]	[Next]
F1 Help F8 Back F9 Abort F1	0 Novt		
Herb Bo back Be Abort HI	Next		

Setup 01 - Database

YaST2 -	susemanager_setup @ su	umal			
Databa	se Settings				
(x) Embedded Database) Remote Database Database Name				
			TOP		
	abase User				
Dat	emanager abase Password ****				1
Rep	eat Password				

[Help]		[Back]		[Abort]	[Next]
	50 DELLE 50 NESSEE 5				[Hevel
Help	F8 Back F9 Abort F	Next			

Setup 01 - SCC

YaST2	susemanager_setup @ sumal		
SCC Se	ttings		
(x)	Connect to SCC SCC Organization Credentials U sername		
	fooo SCC Organization Credentials P assword		

	[Test]		
()	Connect to SUSE Manager for inter-server sync		
[Help]	[Back]	[Abort]	[Next]
		[NOOI C]	Inext
FL Help	F6 Test F8 Back F9 Abort F10 Next		

Setup 01 - First Login

Open a SSH tunnel:

```
$ ssh -Nf -R 0.0.0.0:$high_port:localhost:443 "$user"@"$trainings_
```

Access the WebUI with your browser:

https://training.cust.adfinis-sygroup.ch:"\$high_port"